

## Setup Instructions: Pegasus E-mail Client

Note: If Pegasus has already been installed, go to the next section, **Setup After Installation**.

### Initial Installation:

1. Open Pegasus.
2. Click **Continue installation**.
3. Depending on your setup, click on either **Install NetWare Support** or **No NetWare Support**.
4. You will be asked in which directory Pegasus should be installed. Usually the default is fine, or you can place the program elsewhere. Click **OK** when your choice of directory is complete.
5. Pegasus will also ask what dictionary you want to use during spell checking. Select **Use the US English dictionary by default**.
6. You want to check **Create a Program Manager Group for Pegasus Mail** if you want an icon so you can run Pegasus. Also check **Use Pegasus Mail as a default mailer for MS Internet Explorer** if you would like to use Pegasus mail instead of Internet Mail in Internet Explorer. Now, click **Install Pegasus Mail**.
7. Following the installation, click **Exit**.
8. When you start Pegasus for the first time, you will see a screen that says "Welcome to Pegasus Mail!" Click the button that says **Click here if there will only ever be one person running Pegasus Mail on this computer**. Refer to the last section, **Multiple Users**, for instructions on setting up Pegasus for multiple users or e-mail addresses.
9. Pegasus setup now asks what directory to store your mail in. The default should be fine. Click **OK**.
10. Pegasus will warn you of a possible problem with Windows 95. If you are running 95, note this possibility and the fix for the problem.
11. Pegasus setup now asks if you use winsock.dll. Click **Yes**. Then click on **General settings**.
12. Type your real name in the **Personal name** line. In the **Default reply address**, type your e-mail address: username@psinet.com for a Remote Access account, and username@domain.com for a PSINet e-Mail account. Click on **Network configuration**.
13. You will be prompted for settings. Make sure **Network configuration** is highlighted. For **POP3 host**, enter pop3.psinet.com for a Remote Access account, and psimail.domain.com for a PSINet e-Mail account. For **User name**, type the same username you use to dial in (lowercase). For **Password**, type the same password you use to dial in (lowercase). For **SMTP host**, type smtp.psinet.com for a Remote Access account, and smtp.domain.com for a PSINet e-Mail account. Click **OK**.

## Setup Instructions: Pegasus E-mail Client

### Setup After Installation

1. Click on Tools, Options.
2. Click on General settings.
3. Type your real name in the Personal name line. In the Default reply address, type your e-mail address: user@psinet.com for a Remote Access account, and user@domain.com for a PSINet e-Mail account. Click on Network configuration.
4. You will be prompted for settings. Make sure Network configuration is highlighted. For POP3 host, enter pop3.psinet.com for a Remote Access account, and psimail.domain.com for a PSINet e-Mail account. For User name, type the same username you use to dial in (lowercase). For Password, type the same password you use to dial in (lowercase). For SMTP host, type smtp.psinet.com for a Remote Access account, and smtp.domain.com for a PSINet e-Mail account. Click OK.

### Multiple Users

1. In order for this to work, you must have installed Pegasus Mail in multi-user mode. If you have installed Pegasus in single user mode, re-install it to the same directory, and choose multi-user mode.
2. To add a new e-mail address:
  - Go to the Addresses menu and select **User Management**.
  - Click on the **Add** button, and enter the new login ID and a Personal name.
  - If you want this user to have the ability to alter global settings, click the **Administrator Privileges** box.
3. For multiple users:
  - You will need to set up each user under **Addresses/User Management**. Don't forget that you must have at least one user with administrator privileges. You will need to log in as each individual user to set up their options.
  - Log in as the first user. Under **File/Network Configuration**, put in their login ID and login password.
  - The **POP3 Host** will be pop3.psinet.com for a Remote Access account, and psimail.domain.com for a PSINet e-Mail account.
  - The **SMTP Host** will be smtp.psinet.com for a Remote Access account, and smtp.domain.com for a PSINet e-Mail account.
  - If you wish to have Pegasus automatically check this user's mail at a given interval when they are logged in, you may set the interval under **Advanced options**.

## Setup Instructions: Pegasus E-mail Client

4. For one user with multiple mailboxes:
  - Turn off any mail-checking you have under the regular setup.
  - Select **Extensions/Multi-POP**.
  - Click on **Add**.
  - Put in the login ID and login password for the first mailbox.
  - The **POP3 Host** will be pop3.psinet.com for a Remote Access account, and psimail.domain.com for a PSINet e-Mail account.
  - Select **Delete retrieved mail on host**.
  - If you wish to have Pegasus check this box at a regular interval while Multi-POP is active, you may set the interval under **Connect to this host**. Multi-POP must be active if you want it to check the mail in your mailboxes at a set interval.
  - The **SMTP Host** should be set to smtp.psinet.com for a Remote Access account and smtp.domain.com for a PSINet e-Mail account. You may also enter a custom From: line.
  - Repeat this step for each mailbox you wish to check with Pegasus.